


Sampling & Analysis Methods: Data Gaps at the Libby Asbestos Site



Mary Goldade EPA Region 8 January 17, 2007

Data Gaps in Baseline Risk Assessment

Toxicity Assessment

Epidemiology Studies
Toxicity Studies
(Cancer Stope Factor & Reference Concentration)

Data Data
Collection Evaluation

Sampling/Analysis Methods


Improvements & Validation

Risk Characterization Risk Models

Exposure Assessment

Roadmap

- Sampling Overview
- Analysis Overview
- Method Improvements
 & Verification Needed




Sampling Overview


Sampling/Preparation

 Concentrate asbestos fibers while minimizing matrix effects

Sample Size

- Maximize sample size to maximize analytical sensitivity
- Volume (L) = Flow Rate (L/min) x Time (min)





Validation Needed:



Evaluation of sample filter efficiency for collection of Libby Amphibole is critical to ensure data accuracy

- * Filter pore size (0.8 μm and 0.45 μm)
- Filter composition (mixed cellulose ester and polycarbonate)

Asbestos Fiber Identification

Morphology (physical)

Length, width, aspect ratio (length: width)

Mineralogy (chemical & crystalline)

- Serpentine (chrysotile)
- Amphiboles (e.g., crocidolite, Libby Amphibole, plus many others)



Libby Asbestos

Counting rules & procedures vary with the method of analysis.


Air Analytical Techniques (Briefly!)

Phase Contract Microscopy (PCM)

- Not specific for mineral fibers cat hair cellulose not discernible from asbestos fiber
- Can't observe fibers thinner than 0.25 μm
- PCM-Equivalent Fiber

Electron Microscopy (TEM/SEM)

- Mineralogy is estimated
- Transmission Electron Microscopy & Scanning Electron Microscopy reveal many thin/short fibers not observed by PCM.



Analytical Sensitivity - Balancing Act

Transmission Electron Microscope

Volume of Air (Liters)	#GO	Sensitivity (S/cc)	Approx. Cost
2,500	10	0.0012	~\$80
2,500	30	0.0004	~\$280
2,500	50	0.0002	~\$480

Analytical Sensitivity

Must be low enough for risk assessment

Problem: Analytical counting rules rather than toxicological impacts generally drive what is identified/counted.

Improvement Needed:

Improved understanding of the relationship between morphology and toxicity will allow an appropriate strategy for analytical method development.

Analytical Tools for Soil

Improvement Needed:

Analytical tool(s) needed to measure the presence/absence of Libby Amphibole at levels less than ~0.05% (by weight)

- Validation of the glove box method for Libby Amphibole SOP = EPA Region 10-IEU-001 (Januch 2005)
- Development or refinement of other techniques that isolate concentrate Libby Amphibole while minimizing matrix effects

